

Upgrade Console

index

- Introduction
- GNU/Linux
 - Check version
 - Download the latest version
 - Stop soffid-iamconsole service
 - Locate iam-ear.ear file and upgrade console
 - Restart soffid-iamconsole service
 - Upgrade confirmation
- Microsoft® Windows™
 - Check version
 - Download the latest version
 - Stop soffid-iamconsole service
 - Locate iam-ear.ear file and upgrade console
 - Restart soffid-iamconsole service
 - Upgrade confirmation

Introduction




To update the console from version 1.x to 2.x, download the full installer (not the service pack) and perform the installation.

In other cases, follow the instructions that appear below.

GNU/Linux

Check version

- Current version of your Soffid installation can be obtained by navigating to: Start - Main Menu - Soffid Configuration - Soffid parameters.



- In the table below, the parameter `component.iam.common.version` shows the current installed version.

Parameter	Value	Network	Description
component.iam.common.version	1.6.15		
soffid.schedule.timeStamp	1479313695889		Task scheduler update time stamp
component.iam-core.version	1.6.15		
component.dbtools.version	1.14		
component.jpdm-jpdm.version	3.3.1.GA		


The current iam-ear.ear version.

Download the latest version

First, please download the iam-ear.ear latest version file from: <http://www soffid.com/download/enterprise/>

soffid Download enterprise components

	Soffid Console 1	Download	Get source code
Version:	2.6.0	Download :	Windows Installer Linux / Unix Installer Service pack(ear) 2
Version:	2.5.7	Download :	Windows Installer Linux / Unix Installer Service pack(ear)
Version:	2.4.1	Download :	Windows Installer Linux / Unix Installer Service pack(ear)
Version:	2.3.7	Download :	Windows Installer Linux / Unix Installer Service pack(ear)
Version:	2.3.3-1 Requires: Java 7	Download :	Windows Installer Linux / Unix Installer Service pack(ear)
	Synchronization server	Download	Get source code
	Soffid Full installer [RECOMMENDED]	Download	Get source code
	Connectors Sync server connectors		
	Addons Console addons		
	ESSO Enterprise Single Sign On		



Stop soffid-iamconsole service

Open a command console instance and stop the service:

```
# service soffid-iamconsole stop
```

Locate iam-ear.ear file and upgrade console

- If you are using version 1.x, please go to folder `/opt/soffid/iam-console/jboss/server/default/soffid`; if you are using version 2.x,

please go to folder '/opt/soffid/iam-console-2/soffid'

- Rename the file 'iam-ear.ear' to 'OLD-iam-ear.ear'
- Copy the ear downloaded file from download folder to current directory.
- Rename the file 'Soffid Console-Service pack(ear)-2.6.0.ear', for 'iam.ear.ear'

Restart soffid-iamconsole service

Open a command console instancia and restart the service:

```
# service soffid-iamconsole start
```

Upgrade confirmation

- Verify the service has restarted succesfully by typing the following command and press Intro:

```
# service soffid-iamconsole status
```

- If service is running, next message is shown:

```
● soffid-iamconsole.service - LSB: soffid-iamconsole
   Loaded: loaded (/etc/init.d/soffid-iamconsole; generated)
   Active: active (running) since Mon 2019-04-08 12:30:30 CEST; 4h 39min ago
     Docs: man:systemd-sysv-generator(8)
  Process: 726 ExecStart=/etc/init.d/soffid-iamconsole start (code=exited, status=0/SUCCESS)
    Tasks: 60 (limit: 4915)
   CGroup: /system.slice/soffid-iamconsole.service
           └─1115 /usr/bin/java -server -Dinstall4j.jvmDir=/usr -Dexe4j.moduleName=/opt/soffid/iam-co

abr 08 12:30:30 soffid-NUC7i5BNH systemd[1]: Starting LSB: soffid-iamconsole...
abr 08 12:30:30 soffid-NUC7i5BNH soffid-iamconsole[726]: testing JVM in /usr ...
abr 08 12:30:30 soffid-NUC7i5BNH soffid-iamconsole[726]: Starting soffid-iamconsole
abr 08 12:30:30 soffid-NUC7i5BNH systemd[1]: Started LSB: soffid-iamconsole.
```

- Check your version through the Soffid console:

soffid Start ▾ Addon management

Main Menu

- Processes and tasks
- Resource management
- ▼ Soffid Configuration **1**
 - Tenants
 - Soffid parameters **2**
 - Additional data
 - Agents

Addon management

- User and passwords domains
- Business process definition
- Configure Workflow engine
- Retrieve password configuration
- Authorizations
- Attribute translation tables
- Identity Federation Addon
- Monitoring and reporting
- My Profile

- Check the version of the core files:

soffid Start Configuration Settings Management

Advanced User interface Authentication methods Task engine Cache

Search criteria

Clear criteria

Parameter: _____ Value: _____

Description: _____ Network: _____

Browser

+ Add new - Remove selected


Parameter	Value
masterVersionLevel	102
soffid.schedule.timeStamp	1554374617963
SSOServer	soffid-NUC7i5BNH.null
AutoSSOSystem	SSO
AutoSSOPolicy	S
AutoSSOURL	http://soffid-NUC7i5BNH.null:8080/
seycon.https.port	760
soffid.task.limit	15
soffid.task.mode	manual
tenantDbLevel	1
soffid.ui.docStrategy	com.soffid.iam.doc.nas.comm.DatabaseStrategy
soffid.ui.docPath	-
soffid.ui.docTempPath	/opt/soffid/iam-console-RC2/bin/.../temp
AutoSSOURL	http://master.soffid-NUC7i5BNH.null:8080/
tenantVersionLevel	102
soffid.ui.wildcards	auto
soffid.ui.maxrows	200
soffid.ui.timeout	10000
component.iam-common.version	2.6.0
component.iam-core.version	2.6.0
component.dhntools.version	1.17

Showing only the firsts 200 results. Apply a more restrictive filter to obtain all results.

Microsoft® Windows™

Check version

- Current version of your Soffid installation can be obtained by navigating to: Start - Main Menu - Soffid Configuration - Soffid parameters.



- In the table below, the parameter `component.iam.common.version` shows the current installed version.

The screenshot shows the 'Configuration Settings Management' page. It includes a search criteria section with input fields for 'Parameter', 'Value', 'Description', and 'Network'. Below this is a 'Browser' section with a table of parameters. The table has columns for 'Parameter', 'Value', 'Network', and 'Description'. The first row is highlighted in green and shows the parameter `component.iam.common.version` with a value of `1.6.15`.

Parameter	Value	Network	Description
<code>component.iam.common.version</code>	1.6.15		
<code>soffid.schedule.timeStamp</code>	1479313695889		Task scheduler update time stamp
<code>component.iam-core.version</code>	1.6.15		
<code>component.dbtools.version</code>	1.14		
<code>component.jpdm-jpdm.version</code>	3.3.1.GA		

The current iam-ear.ear version.

Download the latest version

- First, please download the iam-ear.ear latest version file from: <http://www soffid.com/download/enterprise/>



soffid Download enterprise components

	Soffid Console 1	Download	Get source code
Version:	2.6.0	Download :	Windows Installer Linux / Unix Installer Service pack(ear) 2
Version:	2.5.7	Download :	Windows Installer Linux / Unix Installer Service pack(ear)
Version:	2.4.1	Download :	Windows Installer Linux / Unix Installer Service pack(ear)
Version:	2.3.7	Download :	Windows Installer Linux / Unix Installer Service pack(ear)
Version:	2.3.3-1 Requires: Java 7	Download :	Windows Installer Linux / Unix Installer Service pack(ear)
	Synchronization server	Download	Get source code
	Soffid Full installer [RECOMMENDED]	Download	Get source code
	Connectors Sync server connectors		
	Addons Console addons		
	ESSO Enterprise Single Sign On		

Select and download the latest version.

Stop soffid-iamconsole service

- Secondly, please type in search for Windows 'Services.msc' and stop soffid-iamconsole service:




Locate iam-ear.ear file and upgrade

console


- If you are using version 1.x, please go to folder 'C:\Program Files (x86)\Soffid\IAM-Console\jboss\server\default\soffid'; if you are using version 2.x, please go to folder 'C:\Program Files\Soffid\IAM-Console-2\soffid'

Rename the file 'iam-ear.ear' to 'OLD-iam-ear.ear'




- Copy the latest iam-ear.ear file

from you download folder and paste it in the previous folder. Rename the file 'iam-ear-xxx.ear', where xxx is the version number, for 'iam.ear.ear'




Restart soffid-iamconsole service

- Finally, run the soffid-iamconsole service, and that's it!



Upgrade confirmation

- Please, just ensure the task was successfully done. For confirmation, please check your version again in the Soffid panel.



soffid Configuration Settings Management

Search criteria

Clear criteria

Parameter: Value:

Description: Network:

Browser

+ Add new - Remove selected

Parameter	Value	Network	Description
soffid.authentic.kerberos	14430c2d0211		
Component:am-common:version	1.7.4		Task estelove update time stamp
Component:am-common:release	1.4		
Component:dbutils:version	1.14		
Component:dbutils:release	1.1.16		
Component:client:client:am:version	1.8.0		
Component:client:client:am:release	1.8.0 GA		
Component:spring:version	1.2.7		
Component:commons-beanutils:version	1.1		
Component:commons-beanutils:release	1.7.0		
SOFFServer	SOFFFD-V016:soffid.com		
version:core	12		
version:libos:port	700		
soffid.ui.doc:Strategy	es:caib:ham:am:com:LuciaFacSystemStrategy		
soffid.ui.doc:Path	C:\Program Files (x86)\soffid\AM-Console\doc\data		
soffid.ui.doc:TempPath	C:\Program Files (x86)\soffid\AM-Console\doc\temp		
soffid.ui.doc:am:version	1.4		
soffid.ui.doc:am:release	am:1		
soffid.ui.doc:am:release	200		
Component:am:am:version	1.2.3		
Component:am:am:release	2.1.3		
Component:am:am:release	1.5.3		
Component:am:am:release	2.1.3		
Component:am:am:release	2.1.3		
Component:am:am:release	Unknown		
Component:am:am:release	Unknown		
Component:am:am:release	Unknown		

Actú a carácter comodín para la búsqueda
Número máximo de Bus a mostrar en las búsquedas

Now, please check whether there is a new Sync Server Version. In that case, please upgrade it following these steps:

Upgrade Sync Server